Handling-Short Instruction for

PG-USB Cable 9359-1 V1.4

The PG-USB-Kabel is an interface cable for the 15pin PG-Port X4/X5 of a S5 plc. The cable should be connected to the USB-Port (type A-connector). This cable will be active against the plc while the power will be taken from the usb-port of the PC. For some special slot cards for the S5 you can get some special adapters with the several pinning of this card.

This cable can be prolonged with the classic prolongation (pin 2+9 and 6+7 itself drilled) up to 100m 1to1 pin.

In the Case of the Cable are 2 LED's embedded

GREEN lights when data is transferred to the PLC YELLOW lights when data is transferred from PLC to PC

Install the cable

First connect the PG-USB cable into a free USB-Port of your computer. Please download from the below listed web-side the USB-driver for the PG-USB-cable.

Extract the file on your PC and guide the starting hardware-installation-wizard to this folder. The software will install the drivers for the PG-USB cable automatically.

After the driver is installed successfully the COM port is displayed in Control Panel \rightarrow System \rightarrow Device manager \rightarrow COM and LPT \rightarrow Properties (Right mouse click) \rightarrow Extended.

If you changed the COM-Port-Number, restart the PC to activate this COM-Port. After restart choose in the application the selected COM-Port in the configuration.

Using the original Siemens S5 software in a DOS window


Do you use the original Siemens S5 software, then you need to run the S5-patch once. You can download this "Step5 additional driver" also from the named web-side and install it on that PC. Go on with choosing the language. Select the PG-USB cable and confirm with "OK". Press "Install" and choose the folder where the S5 software is installed. The installation routine is now searching for the S5 software. Next you have to select the used COM port. Then the S5 patch will be installed. Press "End" as soon as the installation is completed.





Attention: For the Step5-Original application there **must** be one COM1 to COM4 selected. If necessary change the COM port. Go to

the Control Center, select "System". In the Tab "Hardware", click button "Device manager". In the Device-Manager the virtual COM-Port is listed in the section "Interfaces (COM and LPT)". Right click




"USB Serial Port (COMx)", in the Context Menu choose "Properties". In the following dialog select the tab "Port Settings". Click onto the button "Advanced", in the next dialog you could choose the COM-Port.

Using S5 Original-Software

under Windows 98

A virtual created COM port cannot be used directly from a MSDOS Box (Windows 98). The solution is easy just install the "S5 VCOM for Win98". In the PG-USB menu expand the tree and select the entry "S5 VCOM for Win98". Choose the language and enter the path where the software should be installed. Select the name for the start menu and click next to proceed with the installation. After the End of the Installation the PC must be rebootet. S5 VCOM is installed into the Autostart-Directory and is started every time the PC boots. If an error occurs while installation or starting of driver, a message is shown. If correctly installed, on the bottom-right corner of the Screen a new tray icon is displayed.

This Tray-Icon shows, if a PG-USB-Cable is connected or not, and if a communication is in progress.(S=from PC to S5,E=from S5 zu PC)



In the section State is displayed which Interface-Cable is used for communication and if a connection exists.



In the section virtual Port the following information is shown on the left side is the COM - Port which is used from Windows-Software and on the right side the COM-Port (IO-Ports) of the MS-DOS Box. This COM-Port should be selected in the S5-Software. According which COM - Ports already exists, the next free COM-Port will be used:

existing COM	from S5VCOM used
NONE	COM1 [03F8h,IRQ4]
COM1	COM2 [02F8h,IRQ3]
COM1,COM2	COM3 [03E8h,IRQ4]
COM1,COM3	COM2 [02F8h,IRQ3]
COM1,COM2,COM3	COM4 [02E8h,IRQ3]

In the section Program you could exit the application, change the language of the application or minimize to the tray-icon.

PG 95 / PG 2000

Select under Options → Interface the corresponding virtual COM-Port.

S5 for Windows

In Files → Poperties → Interface select the Protocol "S5" and the virtual COM-Port

Accessories

AG-150-Adapter for PG-USB-Kabel CP525-Adapter for PG-USB-Kabel CP525K-Adapter for PG-USB-Kabel WF470-Adapter for PG-USB-Kabel Sinum-Adapter for PG-USB-Kabel PG-USB Lengthen set

S5-LAN Module (Programming the S5 over Network)

More information to Interface-Cables, also the actual handbooks online under www.process-informatik.de